


Why Single Dish?




Chris Salter
Green Bank & Arecibo Observatories

with **IMMENSE THANKS** to
Darrel Emerson, NRAO Tucson




School on Single-Dish Radio Astronomy. Green Bank, Aug. 2019

What are the Alternatives to Single Dishes?



Single Dish.


Free space propagation & reflection
to bring all signals together in phase



Phased Array.


Cables of just the right length,
to bring all signals together in phase

Interferometer Options



Adding Interferometer or
Phased Array

A single dish with missing metal.



Correlation or
Multiplying interferometer

All aperture synthesis radio telescopes
are made up of multiple correlation
interferometers

Phased Array (Adding Interferometer) vs. Correlation Interferometer

2-Element Phased Array:

Signal voltage into each antenna element: **a, b**

Noise voltage of each antenna amplifier: **A, B**

Before detector:

$$(A + a) + (B + b)$$

After detector:


$$[(A+a) + (B+b)]^2$$

or

$$A^2 + B^2 + a^2 + b^2 + 2.(A.a + A.b + B.a + B.b + A.B + a.b)$$

Time-averaged products of uncorrelated quantities tend to zero, so this averages to just:

$$A^2 + B^2 + a^2 + b^2 + 2.a.b$$



Multiplying or Correlation Interferometer:


•After multiplier: $(A + a).(B + b)$
or

$$A.B + A.b + a.B + a.b$$

•After averaging, uncorrelated products tend to zero, so this becomes just;


$$a.b$$

The averaged output no longer depends on A or B, the internally generated amplifier noise voltages (ignoring statistical fluctuations)




NB:
*multiplication + averaging
= correlation*

In Summary



**Adding Interferometer or
Phased Array**

- $A^2 + B^2 + a^2 + b^2 + 2.a.b$





**Correlation or
Multiplying Interferometer**


- $a.b$

Comparison of Phased Array (Adding Interferometer) vs. Correlation Interferometer


- The **Phased Array (Adding Interferometer)** is the same as the **Single-dish telescope**, (just missing some metal & using more cable instead).
- **Single Dish/Phased Array** are *very* susceptible to changes in receiver gain, and to changes in receiver noise temperature.
- The **Correlation Interferometer** is essentially immune to receiver gain and noise changes.
- Some source distributions, or combination of sources may be *invisible* to the **Correlation Interferometer**. This includes angularly very extended distributions.



A single dish of diameter D
includes all baselines from 0 to D




A correlation interferometer of
separation d , using dishes of
diameter D , includes
all baselines from $d - D$ to $d + D$



Angle on sky = (λ /Baseline) radians


Spatial Frequency is proportional to Baseline



To get an accurate picture of the large scale structure and total flux density in a field, AND ALSO the fine scale detail in a source, you require a combination of both interferometric and single-dish observations.


Make sure that you attend Natalie Butterfield's talk!

The Whole Radio Sky (408 MHz -- $\lambda 73$ cm)



Made with 4 large single-dish telescopes. Contains all the flux in the sky (including the 3 K Cosmic Microwave Background!) Could only have been made with single dishes.


A cross-section through the 408-MHz All-Sky Image at Dec \sim 0 $^\circ$



F.T.



Spatial frequency distribution of the all-sky 408 MHz distribution



Spatial frequency (1/degrees)

Spatial Frequencies: Single Dish vs. Interferometer

- Single Dish has a high-end spatial frequency cut-off in resolution set by its diameter.
- Interferometer has a low-end spatial frequency cut-off set by its minimum antenna separation.
- Sometimes, the Interferometer low frequency cut-off is advantageous.
- Usually, Single Dish maps are analysed in a way that removes the lowest spatial frequencies too; e.g. we don't normally want the 3 K cosmic background in our data.
- The relative flux in low spatial frequencies is typically far greater than that at higher spatial frequencies.
- For cases where we DO want large scale structure, we may HAVE TO USE a Single Dish, likely in combination with an interferometer.

Practical Advantages of Single Dish observing:


- **Spatial Frequency Response**
- **Sensitivity:**
 - Sensitivity in **Jy** (point source) depends just on **collecting area**, SD or Interferometer.
 - Sensitivity in brightness temperature **K** (extended emission) gets WORSE as (Max.Baseline) squared, for the same collecting area – i.e. roughly as $(d/D)^2$.
- Ability to map very extended areas quickly.
- May provide large collecting area with manageable electronic complexity.
- **Simplicity:** One receiver, not N receivers, nor $N(N-1)/2$ correlations.
- BUT *relatively* easy to implement large focal-plane arrays, **including bolometers**, which can increase mapping speed by orders of magnitude.
- Multi-frequency receivers relatively easy investment.
- **Flexibility:** Relative ease of upgrading/customizing hardware to an experiment.
- Relative ease of implementing radar tx systems.
- A single large dish can add significant sensitivity to VLBI arrays.
- Software possibly simpler: "Conceptually" easier to understand for novices.
- Use as test-bed for new receiver systems.
- **Commensality**

Practical Disadvantages of Single Dish Observing

- Limited spatial-frequency response.
- Mechanical complexity replaces electronic complexity.
- Susceptibility to instrumental drifts in gain and noise - don't have the correlation advantage of interferometers.
- Interferometers can *in principle* give high sensitivity and large total collecting area (SKA).
- Aperture synthesis imaging is a form of multi-beaming - arguably obtaining more information from the radiation falling on a telescope than is possible with a single dish.



Things Single-Dish Do Well

- **Pulsar searches** (~2600 known radio pulsar; the vast majority found with single dishes.)



408-MHz Continuum


- **Large-area “background” surveys**




1420-MHz Neutral Hydrogen\ (HI)

Things Single-Dish Do Well (Cont.)

- Molecular line searches





- High-sensitivity VLBI



Arp 220

Things Single-Dish Do Well (Cont.)

- Solar System Radar



- Win Nobel Prizes! (1974, 1978, 1993, 2006)

Single-Dishes: New or Under Construction

- The Large Millimeter Telescope (**LMT/GTM**) of 50-m diameter in Mexico of INAOE & Umass. In service since 2013.
- Sardinia Radio Telescope (**SRT**) of 64-m diameter working to 115 GHz. In service from 2011.
- The Five hundred meter Aperture Spherical Telescope (**FAST**) of 500-m diameter built in China for frequencies to ~ 3 GHz. First light 2016.
- The 6-m sub-mm **CCAT-P** (Cerro Chajnantor Atacama Telescope).

